

# RHCE<sup>Q&As</sup>

Red Hat Certified Engineer — RHCE

## Pass RedHat RHCE Exam with 100% Guarantee

Free Download Real Questions & Answers **PDF** and **VCE** file from:

<https://www.certbus.com/rhce.html>

100% Passing Guarantee  
100% Money Back Assurance

Following Questions and Answers are all new published by RedHat  
Official Exam Center

- ⚙️ **Instant Download** After Purchase
- ⚙️ **100% Money Back** Guarantee
- ⚙️ **365 Days** Free Update
- ⚙️ **800,000+** Satisfied Customers



### QUESTION 1

Configure NFS server to share /common directory with domain30.example.com.

Authenticate the clients devices have the access to it as root user.

Correct Answer: Check the answer in explanation

Explanation/Reference:

```
yum install ?y nfs
```

```
chkconfig nfs on
```

```
chkconfig rpcbind on
```

```
vim /etc/exports
```

```
/common 172.24.30.0/255.255.255.0 (rw,no_root_squash)
```

```
showmount ?e 172.16.30.5
```

```
mount ?t nfs 172.16.30.5:/common /mnt
```

---

### QUESTION 2

Lab 12

Mount the iscsi equipment 192.168.0.254 to /mnt / iscsi boot and set to start automatically. (The experimental laboratory environmental testing, stand?alone test needs to build iSCSI service)

Correct Answer: Check the answer in explanation

Explanation/Reference:

```
[root@server4 Desktop]# iscsiadm --mode discoverydb --type sendtargets --portal 192.168.0.254 --discover
Starting iscsid: [ OK ]
192.168.0.254:3260,1 |iqn.2010-09.com.example:rdisks.server4|
[root@server4 Desktop]# iscsiadm --mode node --targetname iqn.2010-09.com.example:rdisks.server4 --portal 192.168.0.254 --login
Logging in to [iface: default, target: iqn.2010-09.com.example:rdisks.server4, portal: 192.168.0.254,3260]
Login to [iface: default, target: iqn.2010-09.com.example:rdisks.server4, portal: 192.168.0.254,3260] successful.
[root@server4 Desktop]#
```

```
[root@server4 Desktop]# fdisk /dev/sda
WARNING: DOS-compatible mode is deprecated. It's strongly recommended to
switch off the mode (command 'c') and change display units to
sectors (command 'u').

Command (m for help): p

Disk /dev/sda: 33 MB, 33554432 bytes
2 heads, 32 sectors/track, 1024 cylinders
Units = cylinders of 64 * 512 = 32768 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk identifier: 0x106008bb

   Device Boot      Start         End      Blocks   Id  System
/dev/sda1            1         1024        32752   83  Linux
```

```
[root@server4 Desktop]# mkfs.ext4 /dev/sda1
mke2fs 1.41.12 (17-May-2010)
Filesystem label=
OS type: Linux
Block size=1024 (log=0)
Fragment size=1024 (log=0)
Stride=0 blocks, Stripe width=0 blocks
8192 inodes, 32752 blocks
1637 blocks (5.00%) reserved for the super user
First data block=1
Maximum filesystem blocks=33554432
4 block groups
8192 blocks per group, 8192 fragments per group
2048 inodes per group
Superblock backups stored on blocks:
    8193, 24577

Writing inode tables: done
Creating journal (1024 blocks): done
Writing superblocks and filesystem accounting information: done

This filesystem will be automatically checked every 26 mounts or
180 days, whichever comes first. Use tune2fs -c or -i to override.
```

```
[root@server4 Desktop]# blkid /dev/sda1
/dev/sda1: UUID="7ff6dcfc-f38e-4821-8af5-63fb447edb05" TYPE="ext4"
[root@server4 Desktop]# vim /etc/fstab
```

```
#
# /etc/fstab
# Created by anaconda on Mon Aug 15 17:25:29 2011
#
# Accessible filesystems, by reference, are maintained under '/dev/disk'
# See man pages fstab(5), findfs(8), mount(8) and/or blkid(8) for more info
#
UUID=775d457d-6299-4e2b-a4d8-d31660252f01 / ext4 default
ts 1 1
UUID=06e1f8b8-d5ee-47d8-bcfc-0a5ecda3b56c /boot ext4 default
ts 1 2
UUID=c022b102-7fb9-4bd7-b5da-6ddc947d5e26 swap swap default
ts 0 0
tmpfs /dev/shm tmpfs defaults 0 0
devpts /dev/pts devpts gid=5,mode=620 0 0
sysfs /sys sysfs defaults 0 0
proc /proc proc defaults 0 0
[root/yum.iso /mnt/cdrom iso9660 defaults,loop 0 0
-:
```

```
[root@test Desktop]# mount -a
[root@test Desktop]# cat /etc/fstab

#
# /etc/fstab
# Created by anaconda on Mon Aug 15 17:25:20 2011
#
# Accessible filesystems, by reference, are maintained under '/dev/disk'
# See man pages fstab(5), findfs(8), mount(8) and/or blkid(8) for more info
#
UUID=775d457d-6299-4e2b-a4d8-d31660252f01 / ext4 default
ts 1 1
UUID=06e1f8b8-d5ee-47d8-bcfc-0a5ecda3b56c /boot ext4 default
ts 1 2
UUID=c022b102-7fb9-4bd7-b5da-6ddc947d5e26 swap swap default
ts 0 0
tmpfs /dev/shm tmpfs defaults 0 0
devpts /dev/pts devpts gid=5,mode=620 0 0
sysfs /sys sysfs defaults 0 0
proc /proc proc defaults 0 0
/root/yum.iso /mnt/cdrom iso9660 defaults,loop 0 0

[root@server4 Desktop]# df -Th
Filesystem Type Size Used Avail Use% Mounted on
/dev/mapper/vgsrv-root
ext4 3.3G 2.1G 1.1G 68% /
tmpfs tmpfs 246M 176K 246M 1% /dev/shm
/dev/vda1 ext4 248M 30M 206M 13% /boot
/dev/mapper/vgsrv-home
ext4 248M 11M 226M 5% /home
/dev/sda1 ext4 31M 1.4M 28M 5% /mnt/iscsi
```

**QUESTION 3**

Samba configuration requirements are as follows:

1. The Working Group called RHCE
2. Types of user authentication
3. Shared / mnt / storage directory share name for the share
4. The shared directory allows user1 and user2 user has write permissions to other users are read?only, if you need password are redhat
5. only allows the user to access the shared directory domain example.com

Correct Answer: Check the answer in explanation

Explanation/Reference:

```
# yum install ?y samba
# vim /etc/samba/smb.conf

[global]

workgroup = RHCE

security = user

[share]

path = /mnt/storage

write list = user1 user2

hosts allow = .example.com

# ( echo redhat ; echo redhat ) | smbpasswd ?s ?a user1
# ( echo redhat ; echo redhat ) | smbpasswd ?s ?a user2

# service smb start; chkconfig smb on
```

---

#### QUESTION 4

Configure cron as follow:

Clients tom should NOT have access to cron

Correct Answer: Check the answer in explanation

Explanation/Reference:

```
useradd tom
```

```
vim /etc/cron.deny
```

```
tom
```

Effective immediately save and exit.

---

#### QUESTION 5

Configure FTP access as follows:

Download from catalog: / var / ftp / pub using anonymous is allowed

Clients within t3gg.com should NOT have access to FTP on your system

Correct Answer: Check the answer in explanation

---

Explanation/Reference:

```
yum install ?y vsftpd
```

```
chkconfig vsftpd on
```

```
services vsftpd start
```

Deny: uninstall hosts.deny or use iptables

```
vim /etc/hosts.deny
```

```
vsftpd: 172.25.0.0/16
```

```
iptables ?A INPUT ?s 172.25.0.0/16 ?p tcp ?dport 20:21 ?j REJECT
```

```
services iptables save
```

[Latest RHCE Dumps](#)

[RHCE VCE Dumps](#)

[RHCE Practice Test](#)

To Read the [Whole Q&As](#), please purchase the [Complete Version](#) from [Our website](#).

## Try our product !

100% Guaranteed Success

100% Money Back Guarantee

365 Days Free Update

Instant Download After Purchase

24x7 Customer Support

Average 99.9% Success Rate

More than 800,000 Satisfied Customers Worldwide

Multi-Platform capabilities - [Windows](#), [Mac](#), [Android](#), [iPhone](#), [iPod](#), [iPad](#), [Kindle](#)


We provide exam PDF and VCE of Cisco, Microsoft, IBM, CompTIA, Oracle and other IT Certifications. You can view Vendor list of All Certification Exams offered:

<https://www.certbus.com/allproducts>

## Need Help

Please provide as much detail as possible so we can best assist you.

To update a previously submitted ticket:



 <p><b>One Year Free Update</b> Free update is available within One Year after your purchase. After One Year, you will get 50% discounts for updating. And we are proud to boast a 24/7 efficient Customer Support system via Email.</p>	 <p><b>Money Back Guarantee</b> To ensure that you are spending on quality products, we provide 100% money back guarantee for 30 days from the date of purchase.</p>	 <p><b>Security &amp; Privacy</b> We respect customer privacy. We use McAfee's security service to provide you with utmost security for your personal information &amp; peace of mind.</p>
---	---	--

Any charges made through this site will appear as Global Simulators Limited.

All trademarks are the property of their respective owners.

Copyright © certbus, All Rights Reserved.